


Carbonite Server Backup IBM i Agent 9.0

User Guide



© 2023 Open Text. All rights reserved.

This product may be protected by one or more US patents. See https://www.opentext.com/patents for details.

For terms and conditions, see https://www.carbonite.com/terms-of-use/carbonite-general-enterprise-terms-of-service.

Carbonite makes no representations or warranties with respect to the contents hereof and specifically disclaims any implied warranties of merchantability or fitness for any particular purpose. Furthermore, Carbonite reserves the right to revise this publication and to make changes from time to time in the content hereof without obligation of Carbonite to notify any person of such revision of changes. All companies, names and data used in examples herein are fictitious unless otherwise noted.

No part of this document may be reproduced, transmitted, transcribed, stored in a retrieval System or translated into any language including computer language, in any form or by any means electronic, mechanic, magnetic, optical, chemical or otherwise without prior written permission of:

Carbonite LLC 251 Little Falls Drive Wilmington, DE 19808 www.carbonite.com

Carbonite and the Carbonite logo are trademarks of Carbonite, LLC. Product names that include the Carbonite mark are trademarks of Carbonite, LLC. All other products or company names mentioned in this document are trademarks or registered trademarks of their respective owners.

Document History

Version	Date	Description	
1	January 2022	Initial guide for IBM i Agent version 9.0x.	
2	November 2023	Clarified which passwords must be reentered in Reregister an agent with a vault and added link to this section in Complete a disaster recovery. Corrected deferring information in Create backup jobs. Added recommendation in Schedule backups, synchronizations and custom commands re: *CUSTOM job names.	

Contents

1	Int	rodu	uction	6
2	Ins	tall	the IBM i Agent	7
	2.1	Sys	stem Requirements	7
	2.2	Sta	ort the installation or upgrade from a CD	7
	2.3	Sta	ort the installation or upgrade from a save file	8
	2.4	Ins	tall the Agent	9
	2.5	Up	grade the Agent	9
	2.6	Un	install the Agent	9
	2.7	Ins	tall, upgrade or uninstall the Agent in silent mode	10
	2.8	Ins	talled Agent objects and files	10
	2.9	Lic	ense the IBM i Agent	11
3	Ge	t sta	orted with the IBM i Agent	12
	3.1	AG	ENT user profile	12
	3.2	Ac	cess the IBM i Agent main menu	12
4	Coi	nfig	ure an IBM i Agent	13
	4.1	_	eate and manage vault configurations	
	4.1		Create vault configurations	
	4.1	.2	Change vault configurations	
	4.1		Verify vault configurations	
	4.1		Delete vault configurations	
	4.2		register an agent with a vault	
	4.3		eate and manage retention schemes	
	4.3		Create retention schemes	
	4.3		Change retention schemes	
	4.3		Delete retention scheme	
	4.4		nfigure email notifications	
	4.4		d an Agent license	
	4.5		nfigure backup/restore priority and bandwidth throttling	

5	Cre	eate and manage backup jobs	20
	5.1	Create backup jobs	20
	5.1	1 Object (*OBJ) backup job options	23
	5.1	2 IFS (*IFS) backup job options	25
	5.1	3 About System State (*SYS) backups	25
	5.2	Change backup jobs	26
	5.3	Delete backup jobs	27
	5.4	Add a custom command to a backup job	27
	5.5	View a job's log files	28
	5.6	View the agent directory	28
	5.7	View job statuses	28
6	Sch	nedule backups, synchronizations and custom commands	29
	6.1	Change schedules	30
	6.2	Delete schedules	30
	6.3	Enable or disable schedules	30
7	Rui	n ad-hoc (unscheduled) backups	32
	7.1	Seeding and Re-seeding	32
	7.2	Concurrent backup instances	32
	7.3	Save while active	32
8	Syr	nchronize jobs	34
9	Res	solve certificate failures	35
10) Res	store data	36
	10.1	Object (*OBJ) job restore options	38
	10.2	IFS (*IFS) job restore options	39
	10.3	System State (*SYS) job restore options	40
	10.4	About System State (*SYS) restores	41
	10.5	View safeset information	41
11	L Dis	aster Recovery	43
	11.1	Prerequisites	43
	11.2	Complete a disaster recovery	43

12	Bes	t Practices	45
	12.1	Keep your system protection up-to-date	.45
	12.2	Carefully plan your backup jobs	45
	12.3	Journal critical databases and back them up	46
	12.4	Logical File (LF) backup and restore	46
	12.5	Database Files	46
	12.6	Limitations	46
	12.	6.1 IFS backup job limitations	. 47
13	Car	bonite Server Backup Support	48
	13.1	Contacting Carbonite	. 48

1 Introduction

The IBM i (formerly iSeries) Agent backs up data from IBM i (iSeries) systems across a local network or the Internet to a secure vault.

The IBM i Agent must be installed and running on each IBM i system that you want to back up, and each system must be connected to the network. The application runs a background program which, when configured, schedules and runs backups automatically.

You can configure, schedule and monitor the agent using a 5250 terminal emulator Command Line Interface (CLI).

Notes:

- You cannot manage the IBM i Agent using Portal or Windows CentralControl.
- Beginning in IBM i Agent 9.00, the legacy Auto Job Creation tool is no longer available.

2 Install the IBM i Agent

This section describes how to install or upgrade the IBM i Agent. The installation requires that you have the IBM i Agent installation kit and a running IBM i system.

2.1 System Requirements

Before you can install or upgrade the IBM i Agent, the system must meet the following prerequisites:

- QSECOFR or equivalent user profile.
- If you are installing the agent from a CD, a Vary-On optical device connected to CD-ROM.
- If you are installing the agent from a save file, an ACTIVE Ethernet device connected to local network or internet.
- At least 1GB available system storage on *SYSBAS.
- The following licensed programs must be installed and licensed:

Program	Option	Description
5770SS1		Library QGPL
5770SS1		Library QUSRSYS
5770SS1	*BASE	IBM i
5770SS1	1	Extended Base Support
5770SS1	3	Extended Base Directory Support
5770TC1	*BASE	IBM TCP/IP Connectivity Utilities for i

2.2 Start the installation or upgrade from a CD

To start the installation or upgrade from a CD:

- 1. Download the IBM i Agent ISO file from your service provider's website to your computer.
- 2. Burn the ISO file to a CD. For instructions on creating an installation CD, refer to your CD writing software documentation.
- 3. Insert the installation CD into the IBM i server.
- 4. Open a 5250 terminal session. Log on to the IBM i system with the QSECOFR user profile or the equivalent.
- 5. Run the following command to open the IBM i Agent Setup Main Screen:

```
LODRUN DEV (opticalDeviceName)
```

Install or upgrade the IBM i Agent from the CD. See <u>Install the Agent</u> or <u>Upgrade the</u>
 Agent.

2.3 Start the installation or upgrade from a save file

To start the installation or upgrade from a save file:

- 1. Download the IBM i Agent zip file from your service provider's website to your computer.
- 2. Extract the zip file to a temporary location on your computer. The extracted file is a save file.
- 3. Open a 5250 terminal session. Log on to the IBM i system with the QSECOFR user profile or an equivalent.
- 4. Run the CRTLIB EVSAVE command to create a temporary library.
- 5. Run the CRTSAVF EVSAVE/IBMIAGENT command to create a temporary save file:
- 6. Do the following to upload the save file to the IBM i system using FTP:
 - a. On a Windows machine, open a command prompt.
 - b. Run the FTP <IBM i system IP address> command to start an FTP session.
 - c. Enter your user profile (QSECOFR or equivalent).
 - d. Enter your password.
 - e. Enter BIN
 - f. Enter LCD C:\<IBM i Agent save file local location>
 - g. Enter PUT < local file name > EVSAVE / IBMIAGENT
 - h. Enter quit
- 7. On a 5250 terminal, do the following to restore objects from the save file:
 - a. Run the following command to retrieve the saved library name:

```
DSPSAVF FILE (EVSAVE/IBMIAGENT)
```

b. Run the following command to restore all objects from the save file to the EVSAVE library:

```
RSTOBJ OBJ(*ALL) SAVLIB(<saved library>) DEV(*SAVF)
SAVF(EVSAVE/IBMIAGENT) MBROPT(*ALL) ALWOBJDIF(*ALL)
RSTLIB(EVSAVE)
```

Where < saved library > is the library name found in Step 7a.

c. Run the DSPJOBLOG command to verify that objects were restored successfully:

Note: If the objects were restored successfully, an "XX objects restore. 0 not restored to EVSAVE" message appears below the RSTOBJ command.

- d. Run the CALL EVSAVE/ISSETUP command to open the IBM i Agent Setup Main Screen.
- 8. Install or upgrade the IBM i Agent from the save file. See <u>Install the Agent</u> or <u>Upgrade the Agent</u>.

2.4 Install the Agent

Before installing the IBM i Agent, make sure that the following prerequisites are met on the system:

- The AGENT user profile does not exist.
- The AGENT subsystem (*SBSD) does not exist.
- The QCTLSBSD system value is set to either QSYS/QBASE or QSYS/QCTL. If the control
 subsystem is not QBASE or QCTL, use the CHGSYSVAL command to change the QCTLSBSD
 system value to either QSYS/QBASE or QSYS/QCTL before installing the agent. You can revert it
 back to the original value after the agent is installed.

To install the agent:

- 1. On the IBM i Agent Setup Main Screen, press **F6** to perform a fresh installation.
 - *Note:* If a previous version of the IBM i Agent is installed on the system, you cannot perform a fresh installation. See Upgrade the Agent.
- 2. On the license agreement screen, read the license agreement. Press **F6** to accept the agreement.
- 3. Complete the fields on the screen. The default product library is BUAGENT. The default product directory is /buagent.
 - If the installation is successful, a confirmation message appears at the bottom of screen.

2.5 Upgrade the Agent

Before upgrading the agent, be sure that the following prerequisites are met:

- The AGENT user profile is not actively logged on the system.
- No job is running in the AGENT subsystem.

To upgrade the agent:

- 1. Log on to the IBM i system with the QSECOFR user profile or equivalent. You cannot log on as AGENT to upgrade the agent.
- 2. Run the CALL EVSAVE/ISSETUP command to open IBM i Agent Setup Main Screen.
- 3. Enter option 6 to upgrade the agent.
- 4. Enter **YES** in the confirmation screen.

If the upgrade is successful, the agent version is refreshed with the upgraded version. A confirmation message appears at the bottom of screen.

2.6 Uninstall the Agent

Before uninstalling the agent, make sure that the following prerequisites are met:

- The AGENT user profile is not actively logged on the system.
- No job is running in AGENT subsystem.

To uninstall the agent:

- 1. Log on to the IBM i system with the QSECOFR user profile or equivalent. You cannot log on as AGENT to uninstall the agent.
- 2. Run the CALL EVSAVE/ISSETUP command to open the IBM i Agent Setup Main Screen.
- 3. Enter option 4 to uninstall the agent.
- 4. Enter YES in the confirmation screen.

If the agent is successfully uninstalled, a confirmation message appears at the bottom of screen.

2.7 Install, upgrade or uninstall the Agent in silent mode

To install, upgrade or uninstall the agent in silent mode, run the following command:

```
ISSETUP -i|-u|-r cprodlib> cproddir>
```

Include -i to install the agent, -u to upgrade the agent or -r to uninstall the agent.

cprodlib> is the agent library and cproddir> is the agent directory.

For example, to install the agent, you could run one of the following commands:

```
CALL PGM(TESETUP/ISSETUP) PARM('-i' BUAGENT '/buagent')
QSH CMD('/QSYS.LIB/TESETUP.LIB/ISSETUP.PGM -i BUAGENT /buagent')
```

To upgrade the agent, you could run one of the following commands:

```
CALL PGM(TESETUP/ISSETUP) PARM('-u' BUAGENT '/buagent')
QSH CMD('/QSYS.LIB/TESETUP.LIB/ISSETUP.PGM -u BUAGENT /buagent')
```

To uninstall the agent, you could run one of the following commands:

```
CALL PGM(TESETUP/ISSETUP) PARM('-r' BUAGENT '/buagent')
QSH CMD('/QSYS.LIB/TESETUP.LIB/ISSETUP.PGM -r BUAGENT /buagent')
```

2.8 Installed Agent objects and files

The following IBM i Agent objects and files are installed on the system:

- Objects in the BUAGENT library (where BUAGENT is the product library name). This can be verified by running the WRKOBJ BUAGENT/*ALL command.
- Files in the '/buagent' IFS system (where /buagent is the product directory name). This can be verified by running the WRKLNK '/buagent' command.
- AGENT user profile. This can be verified by running the WRKUSRPRF AGENT command.
- AGENT subsystem. This can be verified by running the WRKSBSD BUAGENT/AGENT command.

After a successful installation, the AGENT subsystem is activated automatically. This can be verified by running the WRKACTJOB command.

2.9 License the IBM i Agent

The IBM i Agent has a 30-day trial Agent license when it is first installed. The expiry date for the license is displayed in the Expiry Date field of the Work with License screen.

To obtain a code for a full license, contact your service provider and provide the serial number and software group of the system where the IBM i Agent is installed. This information is displayed on the Work with License screen. You can then enter the license code. See <u>Add an Agent license</u>.

3 Get started with the IBM i Agent

3.1 AGENT user profile

The IBM i Agent installation automatically creates an "AGENT" user profile with the minimum user class and required special authorities. We highly recommend using the AGENT user profile to manage the agent configuration and backup/restore tasks.

To protect critical agent files, *PUBLIC access to files in the agent installation directory is restricted beginning in version 9.00. Low-privilege users can no longer access the agent menu. To grant agent operation access to specific users who do not have *ALLOBJ special authority, a system administrator can grant them private authority or add them to groups with required authority.

To run backups and restores, the user profile must have the following special authorities:

- *ALLOBJ special authority to open and read libraries and objects.
- *SAVSYS special authority for saving system state.

The default password for the AGENT user profile is AGENT. For security reasons, we recommend changing this password. You can change the password using the CHGUSRPRF command. We do not recommend changing any other user profile parameters.

3.2 Access the IBM i Agent main menu

When you sign on to the IBM i server with the AGENT user profile, you will be automatically directed to the ISAGENT menu.

If the initial menu parameter for your user profile is not set to ISAGENT, you can access the ISAGENT menu by running the GO BUAGENT/ISAGENT command (where BUAGENT is the name of the agent product library).

The following menu options are available from the IBM i Agent main menu:

Menu option	Description
1. Agent configuration	Configure vault settings, retention schemes, email notifications, licenses and other Agent settings.
2. Work with Jobs	Create, change and delete jobs, and view safeset and log information. You can also run backups, restores and synchronizations from this menu.
3. Work with schedules	Create, change, delete, enable and disable schedules for backup jobs.
4. Backup	Run an immediate (ad-hoc) backup.
5. Restore	Restore data from a backup.
9. Synchronize	Synchronize backup job information between Agent and the vault.
90. Signoff	Sign off the current user profile.

4 Configure an IBM i Agent

After installing an IBM i Agent, you can configure settings for the agent.

From the Agent Configuration menu, you can access screens for configuring vaults, retention schemes, email notifications, licenses and other Agent settings.

4.1 Create and manage vault configurations

Before the agent can back up data to a vault, the agent must have at least one vault configuration. A vault configuration includes a vault address, account and account credentials. To obtain this information, contact your service provider.

Note: An Agent can have a maximum of 10 vault configurations.

4.1.1 Create vault configurations

To create a vault configuration:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 1 (Work with Vaults).
- 3. On the Work with Vault screen, press F6.
- 4. On the Add Vault Configuration screen, complete the following fields:

Field	Description
Vault Name	The name of a vault where the agent can back up data. An Agent can have a maximum of 10 vault configurations.
	Vault names can be a maximum of 15 characters and can include letters, numbers, and the following special characters: # @ _ and \$. A vault name cannot begin with a number.
Account	The vault account name provided by your service provider. An account name can have a maximum of 40 characters.
User Name	The user name provided by your service provider.
Password	The password provided by your service provider.
Verify password	The password provided by your service provider.
Computer Name	Computer name to use when registering the agent to the vault. The default value is *Host, which is the agent's TCP/IP hostname. Note: You can register the agent multiple times to the same vault by specifying a different computer name in each vault configuration.
Network Address	The network address (IP address or DNS name) for the vault, provided by your service provider.
Port Number	The port that the IBM i Agent uses to communicate with the vault. The port is configured by your service provider. The default value is 2546.

Field	Description
Reconnect delay	The time in seconds that the agent waits before attempting to reconnect to the vault after a communication or session failure. The default value is 30 seconds. The maximum value is 1800 seconds.
	If a reconnection is successful, the backup will continue without data loss. If a reconnection attempt is unsuccessful, the agent waits this amount of time before the next attempt, until the overall timeout (specified by the Retry Timeout value) is reached.
Retry Timeout	The overall amount of time, in seconds, that the agent tries to reconnect to the vault. The default value is 3600 seconds. When the retry timeout value is reached, the backup fails, an error message is added to the log file, and an email notification is sent (if email notifications are configured).
	Note: The Retry Timeout value must be greater than the Reconnect delay value.

Note: The Over the Wire Encryption option is no longer available when you add a vault configuration. Backup data is always encrypted when it is sent to the vault.

4.1.2 Change vault configurations

Note: After you change a vault configuration, the vault configuration is not verified automatically. To verify the vault configuration manually, see <u>Verify vault configurations</u>.

To change a vault configuration:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 1 (Work with Vaults).
- 3. On the Work with Vault screen, enter option **2** for the vault configuration that you want to change.
- 4. On the Change Vault Configuration screen, complete the following fields:

Field	Description
Vault Name	The name of a vault where the agent can back up data. An Agent can have a maximum of 10 vault configurations. Each vault name for the agent must be unique.
	Vault names can be a maximum of 15 characters and can include letters, numbers, and the following special characters: # @ _ and \$. A vault name cannot begin with a number.
Network Address	The network address (IP address or DNS name) for the vault, provided by your service provider.
Port Number	The port that the IBM i Agent uses to communicate with the vault. The port is configured by your service provider. The default is 2546.
Account	The vault account name provided by your service provider. An account name can have a maximum of 40 characters.
User Name	The user name provided by your service provider.
Password	The password provided by your service provider.

Field	Description
Verify password	The password provided by your service provider.
Reconnect delay	The time in seconds that the agent waits before attempting to reconnect to the vault after a communication or session failure. The default value is 30 seconds. The maximum value is 1800 seconds.
	If a reconnection is successful, the backup will continue without data loss. If a reconnection attempt is unsuccessful, the agent waits this amount of time before the next attempt, until the overall timeout (specified by the Retry Timeout value) is reached.
Retry Timeout	The overall time, in seconds, the agent tries to reconnect to the vault. The default is 3600 seconds.
	When the retry timeout is reached, the backup fails, an error message is added to the log file, and an email notification is sent (if email notifications are configured).
	<i>Note:</i> The Retry Timeout value must be greater than the Reconnect delay value.
<i>Note:</i> The Computer Name field also appears but cannot be changed. The computer name is the name used when the agent registered to the vault.	
<i>Note:</i> The Over the Wire Encryption option is no longer available when you change a vault configuration. Backup data is always encrypted when it is sent to the vault.	

4.1.3 Verify vault configurations

To verify a vault configuration:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 1 (Work with Vaults).
- 3. On the Work with Vault screen, enter option **8** for the vault configuration that you want to verify.

A message at the bottom of the screen indicates if the vault configuration was verified or if the verification failed.

4.1.4 Delete vault configurations

You cannot delete a vault configuration if an existing job uses the vault configuration.

When you delete a vault configuration on the agent side, it does not delete the agent registration on the vault. If a vault configuration has been deleted from the agent, you can recover it by reregistering the agent with the vault. See <u>Reregister an Agent with a vault</u>.

To delete a vault configuration:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 1 (Work with Vaults).
- 3. On the Work with Vault screen, enter option **4** for the vault configuration that you want to delete.
- 4. On the confirmation screen, press **ENTER**.

4.2 Reregister an agent with a vault

You can reregister the agent as a computer that was backed up to a vault so you can restore data from the computer that was backed up.

Note: Before reregistering the agent, back up the '/buagent' directory.

To reregister the agent with a vault:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 1 (Work with Vaults).
- 3. On the Work with Vault screen, press **F8**.
- 4. On the Re-register with Vault screen, enter the vault network address, account and user name.
- 5. After the agent connects to the vault, you will be asked to select a registered computer to recover. Once you confirm, any local existing global and job configurations will be overwritten.
- 6. Do the following:
 - a. Re-enter the encryption password for each job.
 - b. Re-enter SMTP credentials.

Note: Before running jobs on a reregistered agent, you must synchronize the jobs. See Synchronize jobs.

4.3 Create and manage retention schemes

A retention scheme specifies how many copies of a backup are stored on the vault, how many days a backup is kept online, and how many days it is held in the archive.

An Agent can have a maximum of 10 retention schemes.

There is always a minimum number of online copies and online days available, even if one is less than the other. For example, if you specify 7 online copies of a backup for 7 online days, there will always be 7 copies even if they are more than 7 days old. In addition, there will always be 7 online days, even if more days have passed.

The oldest safeset is deleted first. You cannot delete all safesets. The most recent safeset is always kept.

4.3.1 Create retention schemes

To create a retention scheme:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 2 (Work with Retention Schemes).
- 3. On the Work with Retention Scheme screen, press F6.

4. On the Add Retention Scheme screen, complete the following fields:

Field	Description
Retention Name	The name of a retention scheme. An Agent can have a maximum of 10 retention schemes. Each retention scheme name for the agent must be unique.
	Retention scheme names can be a maximum of 32 characters and can include letters, numbers, and the following special characters: # @ _ and \$. A retention scheme name cannot begin with a number.
Online Copies (1-999)	The minimum number of safesets to maintain online. When the minimum number of safesets is exceeded, the oldest safeset is deleted.
Online Days (1-9999)	The number of days a safeset is stored on the vault before it expires. When the expiry date is reached, the safeset is automatically deleted. There will always be at least the number of online copies (below), regardless of the setting for online days.
Archive Backup (*YES/*NO)	Enter *YES to archive your backup for a specific number of days. You can then enter a value from 365 to 9999.

4.3.2 Change retention schemes

To change a retention scheme:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 2 (Work with Retention Schemes).
- 3. On the Work with Retention Scheme screen, enter option **2** for the retention scheme that you want to change.
- 4. On the Change Retention Scheme screen, change values in some or all of the fields:

Field	Description
Online Copies (1-999)	The minimum number of safesets to maintain online. When the minimum number of safesets is exceeded, the oldest safeset is deleted.
Online Days (1-9999)	The number of days a safeset is stored on the vault before it expires. When the expiry date is reached, the safeset is automatically deleted. There will always be at least the number of online copies (below), regardless of the setting for online days.
Archive Backup (*YES/*NO)	Enter *YES to archive your backup for a specific number of days. You can then enter a value from 365 to 9999.

4.3.3 Delete retention scheme

To delete a retention scheme:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 2 (Work with Retention Schemes).

- 3. On the Work with Retention Scheme screen, enter option **4** for the retention scheme that you want to delete.
- 4. On the confirmation screen, press **ENTER**.

4.4 Configure email notifications

You can configure email notifications for the agent, so that one or more recipients receive an email when a job fails or succeeds. You must configure email notification for all of the agent's jobs. An email notification cannot be created for a specific job.

To configure email notifications:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 4 (Optional settings).
- 3. On the Optional Settings screen, complete the following fields:

Field	Description
Email Notification	*NONE – Do not send email notifications.
	*ALL – Send email notifications when a backup or restore succeeds or fails.
	*SUCCESS – Send email notifications when a backup or restore finishes successfully.
	*FAIL – Send email notifications when a backup or restore fails.
From Email Address	Email address from which email notifications will be sent.
Recipients	Email notification recipient email addresses.
SMTP Server	Network address of the outgoing mail server (SMTP) that will send the email.
SMTP Server Port	Port number for sending email notifications.
User Name	SMTP username.
Password	SMTP password.
Domain	SMTP domain.

4.5 Add an Agent license

The agent is installed with a 30-day trial license. With this trial license, the agent has full functionality for 30 days. Enter a code for a full license before the end of the 30-day trial period.

To obtain a license code, contact your service provider.

To add an Agent license:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 5 (Work with Agent Licenses).

The Work with License screen shows the agent version, license expiry date and server information. You service provider might need this information to provide you with a full license code.

3. Enter your license code in the License Key field.

4.6 Configure backup/restore priority and bandwidth throttling

You can choose to use all the available network bandwidth for backups and restores, or you can restrict the amount of bandwidth to a specific value.

To configure backup/restore priority and bandwidth throttling:

- 1. On the IBM i Agent Main Menu, enter 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter 6 (Advanced configuration).
- 3. On the Advanced Configuration screen, complete the following fields

Field	Description
Backup/Restore Priority	The backup or restore priority. Available values are 1 to 9. The lower the number, the higher the priority.
Use all available Bandwidth	Enter *YES to use all available network bandwidth when creating a backup. This option is disabling bandwidth throttling. Enter *NO to customize the bandwidth used during a backup.
Limit Bandwidth usage to (Kbps)	The amount of bandwidth in kilobits per second allocated to the backup.
All Day	Enter *YES to apply the bandwidth settings to an entire day. Enter *NO to specify the bandwidth settings to a specific hour of the day.
Start Hours	The hour when bandwidth throttling starts.
Start Minutes	The minutes when bandwidth throttling starts.
End Hours	The hour when bandwidth throttling ends.
End Minutes	The minutes when bandwidth throttling ends.
On the following Days	The days of week when bandwidth throttling is applied.

5 Create and manage backup jobs

Before you can back up data, you must create a job. There is no limit to the number of jobs you can create.

You can select one of these types of data to back up:

- *OBJ Backs up libraries and objects in a native system.
- *IFS Backs up folders and stream files in an Integrated File System.
- *SYS Backs up system state data. System state data is critical to the recovery of the operating system. See <u>About System State (*SYS) backup</u> for more details.

A set of backup jobs can protect your entire system:

- One *SYS job
- Several *OBJ jobs to back up the QSYS system and user data. We recommend at least one
 *ALLUSR job and one *IBM job.

To do a full backup if you configure iASP devices, you must set up two or more *ALLUSR jobs: one for the *SYSBAS ASP device and one for each iASP device.

One or several *IFS jobs to back up the entire *IFS system.

At least one retention scheme must exist before you can create a backup job. See <u>Create and manage</u> <u>retention schemes</u>. When you create a backup job, the default retention scheme (DAILY) is applied to the job. To use a non-default retention scheme, you must create a job with the default retention scheme, and then change the job to assign a different retention scheme.

5.1 Create backup jobs

To create a backup job:

- 1. On the IBM i Agent Main Menu, enter 2 (Work with Jobs).
- 2. On the Work with Job screen, press **F6**.
- 3. On the Add New Backup Job screen, complete the following fields and press ENTER:

Field	Description
Job name	The job name.
	Job names can be a maximum of 30 characters. You can use all alphabet letters and the numbers 0 to 9. Special characters #, @, _, and \$ are allowed.
	Job names exceeding eight characters may appear truncated due to operating system limits. The operating system allows system job names to have up to ten characters, so longer Agent Job names will be truncated. The agent uses a two-character suffix, namely _B, @B, #B, _R, #R, @R to indicate the type of process so that leaves eight characters for the system job name. If there is already another Agent job with the same eight-character abbreviation, then the eighth position will be substituted with a number and the number will be incrementally increased until a unique name is found. The process will continue for the 7th, 6th, and so on until a unique name is found.

Field	Description
Vault name	The name of the vault where the data is backed up. Use the F4 function key to get the list of available vaults.
Data type	Enter the type of data to back up in the job:
	*OBJ – Backs up libraries and objects in a native system.
	 *IFS – Backs up folders and stream files in an Integrated File System. Some file systems are not supported. See IFS device, block, special character and socket files.
	 *SYS – Backs up system state data. System state data is critical to the recovery of the operating system. See <u>About System State</u> (*SYS) backup for more information.

- 4. On the Add New Job screen, complete options for the job data type. See Object (*OBJ) backup job options or IFS (*IFS) backup job options.
- 5. Enter encryption information in the following fields:

Field	Description
Encryption Type	The encryption type used for encrypting data at rest on the vault. *AES256 is the only option for creating new backup jobs with this agent version.
	If an existing job has no encryption or uses another encryption type (e.g., AES 128 bit, Blowfish, DES, Triple DES), which are now set to *ORIG, you can continue to encrypt the job using that type. However, if you change the encryption type for an existing job, you cannot change the encryption type back to the original type. Only *AES256 is available.
	Note: If you change encryption options for an existing job, it will force a reseed. The next backup will take longer than previous delta backups, and the amount of data stored on the vault will increase temporarily, depending on your retention settings.
Password	The encryption password. Maximum 31 characters.
	<i>Note:</i> You must remember your encryption password. Otherwise, you will not be able to recover your data.

6. To specify deferring or other advanced options, press F10 and enter values in some or all of the Additional Parameters fields:

Note: Compression options are not available. To minimize the size of the backup data, the agent now compresses data from all backups using the "Better" compression method.

Field	Description
Deferring: Disable Minutes	Specifies whether to disable deferring for the backup job. When deferring is disabled, the backup runs until it finishes. When deferring is enabled, the backup runs for the specified number of minutes and then pauses until the next scheduled backup time. This can be helpful if you do not want a large backup (e.g., an initial seed) to run when the machine is needed for regular work.
	In the Disable field, enter one of the following options:
	 *YES – Disables deferring and allows the backup to run until it finishes.
	*NO – Pauses the backup after the number of minutes you specify in the Minutes field. After the specified number of minutes, the agent finishes backing up the file that it is currently backing up but does not back up any more files. The backup job then runs again at the next scheduled time. Changes to files that were previously backed up will be backed up, regardless of the backup time window. The agent will traverse the rest of the files to gather metadata for the next backup.
	<i>Note:</i> To ensure that system information is completely backed up, *SYS backup jobs are never deferred.
Quick file scanning	Note: This parameter is only available for *OBJ and *IFS jobs.
	Any data streams that have not changed since the last backup are skipped. This option reduces the amount of data read during the backup process. When *NO is specified, files are read in their entirety, which may result in longer backup times. A read is forced for the following object types, regardless of the Quick File Scanning setting:
	FILE contains multiple members and size greater than OBJSIZ
	FILE is under journaling
	object size greater than OBJSIZ
	• OUTQ
	object name contains special characters (",/,', etc)
Suppress archive-bit process	Note: This parameter is only available for *IFS jobs. Specifies whether the archive-bit of each saved file is altered.
Update history	Note: This parameter is only available for *OBJ jobs.
Space motory	Specifies whether the save history information of each saved object is changed with the date, time, and location of this save operation. Refer to the UPDHST option in the SAVOBJ command for more details.

Field	Description
Log detail	The amount and type of backup information to include in the log files. Enter one of the following options:
	 *FILE – Provides the most detailed information, and is typically used for troubleshooting. Provides information about files that are backed up.
	*NONE – Do not generate log file.
	 *SUMMARY – Provides high-level information, including the vault and Agent version, and backup sizes.
	*DIRECTORY – Provides less detail than the Files logging level. Provides information about folders that are backed up.
Threading Model	On a multi-CPU system, you can use one or more threads to improve backup and restore performance. Enter one of the following options:
	*DEFAULT – Agent selected threading model is used.
	*SINGLE – A single threading model is used.
	*COMBINED – A combined threading model is used.
	*BLOCKPROCESSOR – The block processor threading model is used with up to four processing threads.
	*MAXBLOCKPROCESSOR – The block processor threading model is used with up to five processing threads.
Disable CRC	Disable CRC can improve the performance of backups and restores.
Preserve hard links	Note: This parameter is only available for *IFS jobs.
	Specifies whether hard links are preserved when you back up and restore hard links and the original linked file at the same time. Enter one of the following options:
	*YES – Hard links are preserved when you back up and restore hard links and the original linked file at the same time.
	*NO – A file is backed up as a separate file for each hard link. Hard links are not re-established when the files are restored.

7. Press **ENTER**.

If successful, the new job appears on the Work with Job screen. If a problem occurred, an error message appears at the bottom of the Work with Job screen.

5.1.1 Object (*OBJ) backup job options

Field	Description
ASP Device	The name of the auxiliary storage pool (ASP) device where the data is stored. These are the available options:
	Name – The name of the ASP device.
	*SYSBAS – The system ASP.
	Note: If you configure iASP devices, you must create a separate job for each iASP device. For example, if you have data in SYSBAS and in an iASP device IASP01, create two jobs to back up all user data: ASPDEV(*SYSBAS) INCLUDE((*ALLUSR) and ASPDEV(IASP01) INCLUDE((*ALLUSR).

Field	Description
Include Objects	Objects to include in the backup. The list can include a maximum of 128 entries. Object – The name of the object to back up. *ALLUSR – Saves all objects in the user libraries. QSYS becomes the only legal library name. If you specify more than one entry including *ALLUSR, all the other entries are removed. Refer to LIB option in SAVLIB command for more details. *IBM – Saves all objects in system (IBM) libraries. QSYS becomes the only legal library name. If you specify more than one entry including *IBM, all the other entries are removed. Refer to LIB option in SAVLIB command for more details. *ALL – Saves all objects in a specific library. generic* – Generic names start with one or more valid characters, followed by the wildcard. Library – The library name of the object. If *ALLUSR or *IBM is specified, the library name must be QSYS. When a library name is specified in the Object field, and *LIB is specified in the Type field, the library name must be QSYS. A library cannot be a generic* name. Type – The type of objects to back up. Use *ALL for all types. Note: When you create an *IBM job, five more include entries are automatically added to the job config: All *CMD objects in QSYS library All *MENU objects in QSYS library All *PNLGRP objects in QSYS library All *SBSD objects in QSYS library All *JOBD objects in QSYS library
Exclude Objects	Objects to exclude from the backup. The list can include a maximum of 128 entries. Object – The name of the object to exclude from the backup. *ALL generic* – Generic names start with one or more valid characters, followed by the wildcard. Library – The library name of exclude object. A library cannot be a generic* name. Type – The type of objects to exclude. Use *ALL to exclude all types. Library – The library name of the object. Type – The type of objects to back up. Use *ALL for all types.
Recursive	When backing up a library, specifies whether objects inside the library are included.
Small object size (KB)	Specify the maximum size of object for using the Save File Method . The Save File Method save small object to a save file and backup the save file to vault. This method significantly increases restore performance for a job that contains many small objects, without reducing backup performance.

Field	Description
Save savefile	Specify whether to save the entire save file or just save the save file header.
data	*YES – Save the entire save file.
	*NO – Save the save file object but ignore its data.
	Refer to the SAVFDTA option in the SAVOBJ command for more details.
Spool data (V5R4	Specify whether to save spooled files inside output queue (*OUTQ).
and up)	*ALL – Save all spooled files inside output queue.
	*NONE – Do not save spooled files inside output queue.
	Refer to the SPLFDTA option in the SAVOBJ command for more details.
Save active	This option is used to define check point processing while an object is in used.
	*NONE – Object in use is not saved.
	*SYSDFN – Object can be saved while they are in use.
	*TRIGGER – (obsolete)
	Refer to the SAVACT option in the SAVOBJ command for more details.
Save active/trigger wait time	Specify the amount of time to wait for check point when object is in use. Refer to the SAVACTWAIT option in the SAVOBJ command for more details.

5.1.2 IFS (*IFS) backup job options

Field	Description
Include IFS stream files	The absolute path and file name pattern to include in the IFS backup. The list can include a maximum of 128 items.
Exclude IFS stream files	The absolute path and file name pattern to exclude from the IFS backup. The list can include a maximum of 128 items.
Recursive	When backing up a directory, specifies whether files and sub-directories inside the directory are included.

5.1.3 About System State (*SYS) backups

A System State (*SYS) backup job includes the following items:

Item	Description
User Profiles and Authorization Lists	The same as SAVSECDTA command. It's temporarily saved in save file BUAGNET/SYSSTS1.
Configuration Objects	The same as SAVCFG command. It's temporarily saved in save file BUAGENT/SYSSTS2
System Values	All system values. Refer to WRKSYSVAL *ALL command. It's temporarily saved in user space BUAGENT/SYSSTS3.

Item	Description
TCP/IP configuration	Save the following objects from QUSRSYS library, temporarily to save file BUAGENT/SYSSTS4:
	QAOK*, QAOS*, QATOCIFC, QATOCLIFC, QASO*, QATM*, QATOC*, QAZSP*, QPTMPLPD, QTCP, QTCPASC, QTCPEBC, QTFTP, QTMFQ00021, QTMFTPS, QTMHHTTP, QTMSMTPS, QTMSTRACE, QTPPPOUTQ, QWEBADMIN, QZDATRC, QZHQTRC, QZMF*, QZRCTRC, QZSOTRC
	Note: These objects will be automatically excluded from *OBJ job.
Job schedule entries	Save all *JOBSCD objects from QUSRSYS library, temporarily to save file BUAGENT/SYSSTS5. Note: These objects will be automatically excluded from *OBJ job.

The following table shows differences between a *SYS job and the SAVSYS command:

Data type	*SYS job	SAVSYS command
Security Data (SAVSECDTA)	Υ	Υ
Configuration Objects (SAVCFG)	Υ	Υ
Licensed Internal Code (LIC)	_ 1	Υ
QSYS library	_ ²	Υ
System Values	Υ	-
TCP configurations	Υ	-
Job schedule entries	Υ	-

¹ Licensed Internal Code (LIC) is not backed up by the IBM i Agent. When doing a full system recovery, recover LIC from IBM installation media or from your SAVSYS media.

- *CMD
- *MENU
- *PNLGRP
- *SBSD
- *JOBD

5.2 Change backup jobs

To change a backup job:

- 1. On the IBM i Agent Main Menu, enter 2 (Work with Jobs).
- 2. On the Work with Job screen, enter option 2 for the backup job that you want to change.
- 3. On the Change Job screen, enter new values in the fields you want to change.

² QSYS library data is not backed up in a *SYS job. In an *IBM job, some QSYS library objects are backed up, including:

For field descriptions, see <u>Create a backup job</u>, <u>Object (*OBJ) backup job options</u> and <u>IFS (*IFS)</u> backup job options.

4. To change deferral or other advanced options, press **F10** and then enter values in some or all of the fields.

5.3 Delete backup jobs

You can delete a backup job when it is no longer needed. The delete operation removes the job configuration, metadata files and log files from your local Agent.

Deleting a job will not remove the job configuration, metadata files and existing backups from the vault. If a job is deleted from an agent, you can recover it by re-registering the agent with the vault. See Reregister an Agent with a vault.

To delete a backup job:

- 1. On the IBM i Agent Main Menu, enter 2 (Work with Jobs).
- 2. On the Work with Job screen, enter option 4 for the backup job that you want to delete.
- 3. On the Confirm for Delete Item screen, press **ENTER**.

5.4 Add a custom command to a backup job

You can attach a custom command to a backup job to run a customized operation before or after the backup runs.

Note: To avoid backup failure, a pre-backup command should be tested before it is attached to a backup job.

If a custom command is a batch job (using the SBMJOB command), the agent considers the custom command to be successfully completed once the job is successfully submitted to the system. The user should check the custom command job log for the result.

To add a custom command to a backup job:

- 1. On the IBM i Agent Main Menu, enter 2 (Work with Jobs).
- 2. On the Work with Job screen, enter option **3** for the backup job for attaching a custom command.
- 3. On the Work with Customer Command screen, enter one of the following values in the Command Class field:
 - *PRE When the backup starts, the backup job will kick off the custom command and wait
 until it finishes. If the command fails, the backup will not start and an error message will
 appear in the backup log.
 - *POST When the backup is completed (all data has been committed to vault), the backup job will kick off the custom command and wait for it finish. If the command fails, the backup will still complete with a warning.
- 4. In the Command field, enter the custom command.

5.5 View a job's log files

A log file is created for every backup, synchronize, or restore. You can view a log file to determine if the backup, synchronize or restore operation was successful, the date and time the event completed, and what objects were backed up or restored (when the *FILE log option is specified, see the **Log Detail** field).

To view a job's log files:

- 1. On the IBM i Agent Main Menu, enter 2 (Work with Jobs).
- 2. On the Work with Job screen, enter option **6** for the job for which you want to view log files.

The Display Object Links screen lists the job's logs. Backup logs are named with the safeset number (e.g., 00000001.LOG). Restore logs are named in RSTYYYYMMDD-HHMMSS.LOG format. The SYNCH.LOG is the most current synchronization log file.

3. Enter option 5 for the log that you want to view.

5.6 View the agent directory

The agent directory is created during installation. The agent uses this location to store agent and job configuration files, as well as metadata and log files for jobs.

To view the agent directory:

- 1. On the IBM i Agent Main Menu, enter 2 (Work with Jobs).
- 2. On the Work with Job screen, press F7 to open the agent directory.

Note: This is a shortcut of the WRKLNK '/buagent' command.

5.7 View job statuses

This screen shows all running agent jobs in the AGENT subsystem, as well as related jobs in the QSYSWRK subsystem.

To view job statuses:

- 1. On the IBM i Agent Main Menu, enter 2 (Work with Jobs).
- 2. On the Work with Job screen, press **F10** to view the job statuses.

Note: This is a shortcut of the **WRKACTJOB SBS(AGENT QSYSWRK)** command.

6 Schedule backups, synchronizations and custom commands

After creating a backup job, you can create one or more schedules for running the job automatically. You can also schedule synchronizations and pre-defined custom commands.

The agent uses the built-in IBM i job scheduler to start backups, synchronizations or pre-defined custom commands. Once a job schedule entry is created, you can find the corresponding job entry in the WRKJOBSCDE command.

Important: Do not use the IBM Advanced Scheduler to schedule agent jobs. The agent job scheduler requires multi-threading. The IBM Advanced Scheduler uses the RCLRSC command, which is not compatible with multi-threaded applications.

To schedule a backup, synchronization or custom command:

- 1. On the IBM i Agent Main Menu, enter option 3 (Work with schedules).
- 2. On the Work with Schedule screen, press F6.
- 3. On the Work with Scheduler screen, complete the following fields, and press ENTER:

Field	Description
Command	Enter the type of operation to schedule:
	*BACKUP – Schedule a backup.
	 *SYNCH – Schedule a job synchronization, where the agent checks which safesets for the job are online and available for restore. *CUSTOM – Schedule a custom command or user script to run.
Job Name	The name of a job. Press F4 to retrieve a job list. Note: To ensure that *CUSTOM job names are unique on the Work with Schedule screen, we recommend a maximum of 8 characters in each *CUSTOM job name. The Work with Schedule screen only shows the first 8 characters of each *CUSTOM job name.

4. Enter values in any of the following fields that appear:

Field	Description
Retention name	The name of a valid retention scheme. Press F4 to view a list of retention schemes.
Command cycle	The frequency that the schedule runs (see the Frequency field in the WRKJOBSCDE command). These options are available: • *WEEKLY • *MONTHLY
Minute/Hour	The time for the job to start.
Day of week	The day of the week for the job to run.
Date of month	The date of the month for the job to run.
Customer command	Custom command or user script to schedule.

Quick File Scanning	Any data streams that have not changed since the last backup are skipped. See <u>Create backup jobs</u> for more information.
Deferring	Define the behavior when a backup job reaches a specified amount of time. See <u>Create backup jobs</u> for more information.

6.1 Change schedules

Once a job schedule entry is changed, you can find the associated changes in the corresponding job entry in the WRKJOBSCDE command.

To change a schedule:

- 1. On the IBM i Agent Main Menu, enter option 3 (Work with schedules).
- 2. On the Work with Schedule screen, enter option 2 for the schedule that you want to change.
- 3. On the Work with Scheduler screen, enter values in any of the following fields that appear:

Field	Description
Retention name	The name of a valid retention scheme. Press F4 to retrieve a retention list.
Command cycle	The frequency that the schedule runs (see the Frequency field in the WRKJOBSCDE command). These options are available:
	• *WEEKLY
	*MONTHLY
Minute/Hour	The time for the job to start.
Day of week	The day of the week for the job to run.
Date of month	The date of the month for the job to run.
Quick File Scanning	Any data streams that have not changed since the last backup are skipped. See Create backup jobs for more information.
Deferring	Define the behavior when a backup job reaches a specified amount of time. See Create backup jobs for more information.

6.2 Delete schedules

To delete a schedule:

- 1. On the IBM i Agent Main Menu, enter option 3 (Work with schedules).
- 2. On the Work with Schedule screen, enter option 4 for the schedule that you want to delete.
- 3. On the Confirm for Delete Item screen, press ENTER.

When a job schedule entry is deleted from the Work with Schedule screen, the corresponding job entry in the WRKJOBSCDE command will be removed.

6.3 Enable or disable schedules

To enable or disable a schedule:

- 1. On the IBM i Agent Main Menu, enter option 3 (Work with schedules).
- 2. On the Work with Schedule screen, do one of the following:

- To disable a schedule, enter option **3** for the schedule.
- To enable a schedule, enter option **6** for the schedule.

When a schedule is enabled or disabled from Work with Schedule screen, the status of the corresponding job entry in the WRKJOBSCDE command will be changed to HLD (hold) or SCD (scheduled).

7 Run ad-hoc (unscheduled) backups

After a backup job is created, you can run the backup at any time, even if the job is scheduled to run at specific times.

To run an ad-hoc (unscheduled) backup:

- 1. Do one of the following:
 - On the IBM i Agent Main Menu, enter option 4 (Backup). On the Run Backup screen, enter the name of the job that you want to run. Press F4 to retrieve a job list.
 - On the IBM i Agent Main Menu, enter option 2 (Work with Jobs). On the Work with Job screen, enter option 7 for the job that you want to run.
- 2. On the Run Backup screen, complete the following fields:

Field	Description
Retention Scheme	The name of a valid retention scheme. Press F4 to retrieve retention list.
Quick File Scanning	Any data streams that have not changed since the last backup are skipped. See Create backup jobs for more information.
Disable Deferring	Define the behavior when a backup job reaches a specified amount of time. See <u>Create backup jobs</u> for more information.
Defer after	A maximum amount of time (in minutes) that the backup job can run. See Create backup jobs for more information.

7.1 Seeding and Re-seeding

When you run a backup job the first time, a "seed" backup is created on the vault. This seed backup contains all the data selected for backup in the job. Subsequent backups are much smaller and only include changes (deltas) that have occurred since the last backup.

If the encryption type or password has changed since the last backup, the next backup will automatically be a re-seed.

In the case of a re-seed, your backup will take longer to complete and a message about re-seeding is created in the log file.

7.2 Concurrent backup instances

A backup job cannot have two running instances at the same time. If you start a backup job when another backup job is running, the second job will not start until the first job finishes. The other instance will stay in SEMW (semaphore wait) status until the running backup finishes.

7.3 Save while active

An object backup (*OBJ) job uses the IBM i save-while-active function to save an object while it is in use by another job. This function allows you to back up your data without stopping active processes. For more details about the save-while-active function, see articles in the IBM Knowledge Center: http://www.ibm.com/support/knowledgecenter/ssw_ibm_i_73/rzaiu/rzaiu/rzaiu/sou.htm

The agent includes this function setting in an *OBJ job configuration. However, the agent currently only supports the *SYSDFN (system-defined synchronization) option, which means that objects in the backup job might reach check points at different times even though they are in the same library. This occurs because the agent saves each object individually. Using the *SYNLIB (full synchronization) or *LIB (library synchronization) options will take much longer for the backup job to complete check point processing.

To protect your critical data in consistent mode, we recommend you journal the objects, enable the save-while-active function in the backup job, and use another backup job to back up the journals (*JRN) and journal receivers (*JRNRCV).

If your critical data is not currently configured for journaling, refer to articles in the IBM Knowledge Center for instructions on setting up journaling:

http://www.ibm.com/support/knowledgecenter/ssw ibm i 73/rzaki/rzakikickoff.htm

Here is an example:

- 1. Create a single journal for each library to be backed up. This simplifies administration and adds the journal and receivers in the correct library.
- 2. Create the main job to back up all objects and data and specify two exclusions for *JRN and *JRNRCV object types. Specify *SYSDFN in the save active parameter.
- 3. Create a separate job for *JRN and *JRNRCV objects.

Running backups and restores in the proper sequence is very important. If the backup sequence is not correct and data is updated while the backup is running, some journal receivers might not contain all the data required for point-in-time recovery. If the restore sequence is not correct, some objects might not be journaled after the restore.

The proper backup sequence is:

- 1. Run the main backup job.
- 2. Run the *JRN and *JRNRCV job.

The proper restore sequence is:

- 1. Restore *JRN and *JRNRCV.
- 2. Restore other objects.
- 3. Apply the journal back to the point in time.

8 Synchronize jobs

When you synchronize a job, the agent checks which safesets for the job are online and available for restore, and performs the following tasks on the agent:

- Updates safeset status information.
- Recreate the delta file (DTA), if the most recent delta file is missing.
- (Optional) Resynchs catalog files that are not available on the agent system.

A manual synchronization is required before running backup jobs on agents that have been reregistered to a vault.

To synchronize a job:

- 1. Do one of the following:
 - On the IBM i Agent Main Menu, enter option **9 (Synchronize)**. On the Synchronize screen, enter the name of the job you want to synchronize. Press **F4** for a job list.
 - On the IBM i Agent Main Menu, enter **2 (Work with Jobs)**. On the Work with Job screen, enter option **8** for the job you want to synchronize.
- 2. To resynchronize a missing catalog file for the job, press **F10** on the Synchronize screen. Enter ***YES** to resynch the missing catalog file.

9 Resolve certificate failures

Beginning with IBM i Agent 9.00 and Director version 8.60 vaults, when an IBM i Agent tries to connect to a vault where certificate pinning is enabled, it checks whether the public key of the vault certificate is the same as when the agent previously connected to the vault (e.g., to run a backup or restore).

If the public key of the vault certificate is different, the agent reports a certificate failure and will not connect to the vault unless you re-pin the certificate. If a certificate failure occurs when the agent tries to connect to a vault to run a backup, restore or synchronization, a certificate failure message appears in a log file. If a certificate failure occurs when the agent tries to verify a vault connection or re-register to a vault, a vault certificate cache is not found message appears in the terminal.

If a certificate failure is reported, please contact your IT security staff or service provider to determine whether the certificate change was expected or whether further investigation is required.

If the vault certificate change was expected, you can re-pin the vault certificate. When you re-pin a certificate, the agent securely records the new public key of the certificate. Backups and restores can then continue.

To resolve a certificate failure:

- 1. On the IBM i Agent Main Menu, enter option 1 (Agent configuration).
- 2. On the Agent Configuration menu, enter option 7 (Re-pin Vault Certificate).
- 3. Enter *YES.

10 Restore data

There are several scenarios for restoring IBM i data:

- To recover one or more objects or IFS stream files. You can restore them to their original location, overwriting any that are there, or restore them to a different location as desired.
- To restore data that was backed up on one system to another system.
 - *Note:* The destination machine must have the same operating system version as the machine where the data was backed up or a later operating system version. The agent cannot restore data to a machine with an earlier operating system version. For example, if data is backed up on a V7R4 system, it cannot be restored to a V7R3 system.
- To recover a complete system (i.e., perform a disaster recovery) when the original system has been lost. See <u>Disaster Recovery</u>.

Note: In a disaster recovery scenario, the operating system of the restore system must be the same as the backup system.

To restore data:

- 1. Do one of the following:
 - To view safeset information before restoring data:
 - i. On the IBM i Agent Main Menu, enter **2 (Work with Jobs**). The Work with Job screen shows backup jobs.
 - ii. On the Work with Job screen, enter **9 (Restore Safeset)** for the job from which you want to restore data. The Display Safeset screen shows available safesets, including the safeset numbers, backup time and status.
 - iii. (Optional) To view more information about a safeset, enter **5 (Display)** for the safeset. The Display Safeset Detail screen shows the information described in <u>View safeset</u> information. Press **F12** to return to the Display Safeset screen.
 - iv. On the Display Safeset screen, enter option **9 (Restore)** for the safeset from which you want to restore. The Run Restore screen appears.
 - To start a restore without viewing safeset information:
 - i. On the IBM i Agent Main Menu, enter **5** (Restore).
 - ii. On the Run Restore screen, enter the name of the job from which you want to restore data. Press **F4** to view a job list.

2. On the Run Restore screen, complete the following fields:

Note: The Password and Verify Password fields now appear at the bottom of the Run Restore screen instead of on a separate pop-up screen. If you are restoring encrypted data, you must page down and enter the password before pressing Enter to start the restore.

Field	Description
Safeset No	The safeset number to restore data from.
	 *LASTONLINE – restore from the most recent backup.
	• 1-9999999 – specified a safeset number
	Note: A sequential number is assigned to each safeset after every backup.
Data Type	The data type of this backup job. These are available options:
	*OBJ - to restore libraries and objects in the native system.
	*IFS - to restore folders and stream files in the Integrated File System.
	*SYS - to restore system state data.
Allow object differences	Specifies whether differences are allowed between the saved objects and the restored objects. These are the available options:
	• *NONE
	• *ALL
	• *AUTL
	*COMPATIBLE
	• *FILELVL
	• *OWNER
	• *PGP
	See the ALWOBJDIF option in the RSTOBJ command for each option specification.
Log detail	The amount and type of backup information to include in the log files. Choose from these options:
	 *FILE – Provides the most detailed information, and is typically used for troubleshooting. Provides information about files that are backed up.
	*NONE – Do not generate log file.
	 *SUMMARY – Provides high-level information, including the vault and Agent version, and backup sizes.
	 *DIRECTORY – Provides less detail than the Files logging level. Provides information about folders that are backed up.
Password and Verify Password	Type the encryption password for the backup job. Note: The Password and Verify Password fields are the last fields on the Run Restore screen. If these fields do not appear, the backup data is unencrypted and a password is not required for restoring the data.

- 3. Complete fields required for the job data type. See <u>Object (*OBJ) job restore options</u>, <u>IFS (*IFS) job restore options</u> or <u>System State (*SYS) job restore options</u>.
- 4. Press Enter.

If the restore request was submitted successfully, the following message appears: Restore job ... has been submitted to agent subsystem.

If there was a problem with the restore request, an error message appears. For example, if you did not enter a required encryption password, the following message appears: *Error*: safeset# *is encrypted safeset, input correct encryption password.*

10.1 Object (*OBJ) job restore options

Field	Description
Include objects	The objects to include in the restore. The list can include a maximum of 128 items. You can configure these options:
	 Name – The name of the object to restore. Specify a valid object name or generic name to restore one or more objects, or specify *ALL to restore all objects in the specified library.
	Library – The name of the library to restore.
	Type – The object type to restore. Specify *ALL to restore all types.
	Note: Type *LIB will only restore the library object.
Exclude objects	The objects to exclude from the restore. The list can include a maximum of 128 items. You can configure these options:
	 Name – The name of the object to exclude from the restore. Specify a valid object name or generic name to exclude one or more objects, or specify *ALL to exclude all objects in a library.
	Library – The name of the library to exclude from the restore.
	Type – The object type to exclude from the restore. Enter *ALL to exclude all types.
	Note: When type is specified to *FILE, you cannot use generic object name. However, *ALL is allowed.
Data base member option	The database member restore option for database file exists on the system. These are the available options:
	• *ALL
	• *MATCH
	• *NEW
	• *OLD
	For more information, see the help text for the MBROPT option of the native operating system RSTOBJ command.
Spool file data	Restores spooled file data and attributes. These are the available options:
	*NEW – Select this option to restore spooled file data saved with the output queue if it does not currently exist.
	*NONE – Do not restore spooled file in output queue (*OUTQ)
	For more information, see the help text for the SPLFDTA option of the native operating system RSTOBJ command.

Field	Description
Restore Library	The library to restore to. You select the original source library, or a different one.
	Name – Restore to a named library.
	*SOURCE – Restore to original library.
	Note: The agent will create the library if it does not exist, using default attributes and authorities.
Restore ASP Device	Restores data to an auxiliary storage pool (ASP) device. These are the available options:
	Name – The name of the ASP device to which you want to restore data.
	 *SAVASPDEV – Data is restored to the same ASP device from which it was saved.
Restore ASP Number	Objects are restored to the auxiliary storage pool (ASP) from which they were saved or to the system ASP (ASP number 1) or to a basic user ASP (ASP numbers 2 through 32).
File	Specify the restore option if an object already exists.
Overwrite/Rename Obj	*OVRWRT – Overwrite all existing objects without asking.
Obj	*PMTOVRWRT – Prompt for overwrite option on each existing object.
	*NOOVRWRT – Do not overwrite if object exists.
	Note: When you choose the *PMTOVRWRT option, the main restore job will be pause on MSGW status when an existing object is detected, you should run the WRKACTJOB SBS(AGENT) command. Use option 7 (Display Message) to input the overwrite option.
Ignore security data	Turn on or off the granting of private authorities on an object after it is restored.
	 *YES – Ignore the security data and stop the GRTOBJAUT command after object is restored.
	 *NO – Issue the GRTOBJAUT command to grant private authorities after object is restored. When this option is used, an authorization list or user authorities that were added for an object after the backup will not be changed or removed when the object is restored.
	It is recommended that you enter *YES to improve restore performance. You can later run the RSTAUT command to set private authorities.
No. of Jobs for small objects	The number of jobs to run concurrently for restoring the objects backed up by the Save File Method . You can enter values from 1-8. The default is 4.

10.2 IFS (*IFS) job restore options

Field	Description
Include IFS stream files	The IFS stream files to restore. The list can include a maximum of 128 entries.
	 Absolute path – The absolute path for the stream files saved on the vault.
	File – A name pattern for files to restore.
	Recursive – Includes sub-directories in the restore.

Field	Description
Exclude IFS stream files	The IFS stream files to exclude from the restore. The list can include a maximum of 128 entries.
	 Absolute path – The absolute path for the stream files saved on the vault.
	File – A name pattern for files to exclude from the restore.
	Recursive – Excludes sub-directories in the restore.
Destination	The directory to restore. It must be an absolute path.
	Name – Restore to a named directory.
	*SOURCE – Restore to original directory.
	Note: The agent will create the directory if it does not exist, using default attributes and authorities.
File	Specify the restore option if an object already exists.
Overwrite/Rename Options	*OVRWRT – Overwrite all existing files without asking.
Options	*PMTOVRWRT – Prompt for overwrite option on each existing file.
	*NOOVRWRT – Do not overwrite if the file exists.
	 *RNMINC – Renames the restoring (incoming) file with a unique number (0001, 0002) appended to the file name if that file exists.
	 *RNMEXT – Renames the existing file with a unique number (0001, 0002) appended with the file name, and then restore the file with original name.
	Note: When you choose *PMTOVRWRT option, the main restore job will be pause on MSGW status when an existing object is detected, you should run WRKACTJOB SBS(AGENT) command, use option 7 (Display Message) to input the overwrite option.
Create sub-file	These are the available options:
	*YES – Recreates the restored file structure like the backup structure.
	*NO – Files are added to the top level, and no sub-files are created.

10.3 System State (*SYS) job restore options

Field	Description
System states	Specify the type of system data to restore. These are the available options:
	 *ALL – All system state data.
	 *CFG – Configuration Objects (RSTCFG)
	 *USRPRF – User profiles (RSTUSRPRF)
	 *SYSVAL – All system values.
	 *QUSRSYS – TCP/IP configuration files in QUSRSYS library.
	 *JOBSCD – Job schedule objects in QUSRSYS library.

Field	Description
Prompt RSTxxx	These are the available options:
command	 *YES – Agent will prompt RSTCFG and RSTUSRPRF commands for user to specify different options.
	 *NO – No prompting, agent completes each restore command with default options.

10.4 About System State (*SYS) restores

System State restores must be run on the console. The console device is usually DSP01. This is because restore user profiles (RSTUSRPRF) require the system to run in a restricted state (ENDSYS or ENDSBS *ALL commands). There are more restrictions applied by the RSTUSRPRF and RSTCFG commands. Refer to information about these commands for more details.

There are two steps for system state restore:

- **Step 1**: Agent restore safe files and user space object from vault to local agent product library.
- Step 2: put the system to restricted state, issue restore commands to restore each part of data.

On the RESTORE command, you can choose which part of the system state data to restore, or you can specify *ALL to restore all of them.

Note: The temporary save files remain in the agent product library, except system values, you can manually restore other parts of system state from save files.

Restoring TCP data may involve a network interruption. This occurs because the TCP configuration is being overwritten by the restore. You may need to review the TCP configuration after restore.

If you restore the system value, the system IPL might need to apply system value changes. Refer to each system value for more information.

For more *SYS restore information, please refer to <u>Disaster Recovery</u>.

10.5 View safeset information

As described in <u>Restore data</u>, you can view information about a job's safesets in the vault when starting a restore.

The Display Safeset Detail page shows the following information:

Field	Description
Job Name	The name of the job that created the safeset.
Catalog Number	The sequential number assigned to this safeset.
Location	The name and address of the vault where this safeset is kept.

Field	Description
Status	The safeset status. These options are available:
	Online – You can use the safeset for a restore.
	 Work Area – The data is in transition to Online status. You can either wait for the system to change the status, or you can execute a Synchronize command
	Archived – The safeset is stored off-line from the vault.
Backup Time	The date and time the safeset was created.
Backup Type	The type of backup.
Storage Size	The size of backup. These fields are available:
	Original – The size of the original backed up data.
	Deltized – The amount of deltized data (zero for the initial seed).
	Compressed – The size of the data stored on the vault.
Retention	The retention plan for the safeset. These fields are available:
	Days – The number of days this safeset is kept.
	Copies – The number of backup copies kept.
	Archived Days – The number of days an archive copy is kept.
Encrypted	Indicates whether the backup data was encrypted.
Compressed	Indicates whether the backup data was compressed.
Media Type	The type of media used to store the backup data.
Expiry	The date the safeset will be deleted.

11 Disaster Recovery

In the event of a system disaster where the source (IPL) disk is lost, you will need to recover or rebuild the system from the ground up.

Important: For detailed disaster recovery information, please contact your service provider.

11.1 Prerequisites

Before completing a disaster recovery, the system must have:

Valid backups.

You need valid backups (such as *SYS, *ALLUSR, *IBM, *IFS) to protect the entire source system. Valid safesets must be stored on a vault.

• A basic operating system.

The basic operating system includes **Licensed Internal Code** (LIC), **57xxSS1** (option *BASE, Library QGPL and Library QUSRSYS). You can either install from IBM supplied media, or restore from SAVSYS media.

Network access to a vault.

You need to have the licensed program 57xxTC1 installed on the system. TCP/IP interface needs to be configured and enabled, and have access to the vault.

An IBM i Agent.

An up-to-date agent must be installed on the IBM i system.

11.2 Complete a disaster recovery

This section provides a high level view of how to recover an IBM i system. For detailed disaster recovery information, please contact Support.

To complete a disaster recovery:

- 1. Install the Licensed Internal Code (LIC) and the operating system (OS) from IBM supplied media or SAVSYS media.
- 2. Restore the QGPL and QUSRSYS libraries from IBM-supplied media, or from SAVSYS media if they are saved on SAVSYS media.

Note: We recommend backing up the QGPL and QUSRSYS libraries to the same SAVSYS media for disaster recovery.

- 3. Install the following license programs from IBM supplied media:
 - 57xxSS1 option 1
 - 57xxSS1 option 3
 - 57xxTC1 option *base

Where xx is the licensed program code for your OS level

4. If PTFs are required for the specific OS version, apply the PTFs. See <u>Prerequisites</u>.

- 5. Configure TCP/IP connectivity to the LAN/WAN.
- 6. Install the IBM i agent. If you install the agent on the original system, the original agent license key can be re-used. If you install the agent on a new system, please contact your Service Provider for a new license key.
- 7. Reregister the agent with the vault to recover the original agent configuration and jobs. See Reregister an agent with a vault.
- 8. If the system is rebuilt from IBM supplied media, you need to restore System State (*SYS) job first.
- 9. Restore *IBM job
- 10. Restore *ALLUSR job.
- 11. Restore user data from other jobs.
- 12. Restore *IFS jobs.
- 13. Run the RSTAUT command to apply private authorities.
- 14. Restart the system.

12 Best Practices

12.1 Keep your system protection up-to-date

Before using the IBM i Agent to protect your data, we recommend that you have a completed full system (SAVE 21) media backup of the original system.

When using the IBM i Agent to protect your system, we recommend that you periodically have a system data (SAVSYS) media backup. SAVSYS saves the Licensed Internal Code (LIC) and the operating system, as well as security data (SAVSECDTA) and configuration objects (SAVCFG). This could help you quickly rebuild your operating system.

We also recommend saving the QGPL and QUSRSYS libraries to SAVSYS media, typically when you a PTF is applied. This helps keep your PTF level up-to-date in a disaster recovery.

12.2 Carefully plan your backup jobs

Plan your backup jobs carefully to cover your entire system and critical user data. We recommend you at least have:

- One *SYS job to back up the system state
- One *IBM job to back up IBM supplied libraries.
- One or more separate *OBJ and *IFS jobs to back up critical user data.
- One or more separate *OBJ jobs to back up Journal (*JRN) and Journal Receiver (*JRNRCV)
- One *ALLUSR job to cover the rest of the user data, excluding data covered by other *OBJ jobs.
- One *IFS job to cover the rest of the IFS data, excluding data covered by other *IFS jobs.
- If you want to protect spooled files, create one or more *OBJ jobs for output queue (*OUTQ) only with SPLFDTA(*ALL), and exclude *OUT object from other jobs.

Also plan your backup windows and job scheduling carefully. Delta backups significantly reduce backup times, but other tips can maximize your system resources and avoid affecting business hours:

- Separate jobs can run in parallel, except for *SYS jobs. *SYS jobs run quickly, so run them exclusively. Consider running approximately 3 jobs per available processor.
- Keep the job size small. If a job is big, divide it. For *OBJ jobs, keep the total object count per job to 10,000 or less.
- Keep referenced objects in one job. If you have referenced PF and LF in different libraries, save them in a single job.
- Create separate jobs for volatile objects like databases and journal receivers, and for nonvolatile objects like programs and service programs even if they reside in the same library.
- Schedule jobs to back up journals and journal receivers to start after jobs to back up databases are completed.

12.3 Journal critical databases and back them up

The IBM i Agent is not a replication solution; it is a data protection solution. If you need to protect your critical databases in a consistent state, we recommend the following:

- Journal the critical database files
- Back up the database files, with save-while-active.
- Back up journals and journal receivers, with save-while-active.

When you need to restore a databases, restore the journal and journal receiver first and then restore the database files. You can then move transactions backwards or forwards using journal entries.

12.4 Logical File (LF) backup and restore

We recommend you include associated physical files and logical files in one job, to keep them as close as possible.

The IBM i Agent only backs up the logical file header. No access path is saved in a safeset. When it is restored, the agent submits a separate job in the AGENT subsystem to rebuild the access path.

Logical files are backed up and restored in the following way:

- All logical files included in the job are queued to the end of safeset. In the backup log, you should see all logical files are listed at the end.
- Logical files are restored at the last sequence of safeset.
- The access path is rebuilt.

12.5 Database Files

Because IBM limits access to deleted record information, deleted records will not be restored during a restore. Because some very old AS400 applications relied on relative record numbers for indexing, you may need to check with your application provider to see if you need to be concerned with relative record numbers and deleted records.

Note: IBM strongly discourages the use of relative records numbers in applications since it is a system controlled value and gets changed whenever a RGZPFM command (database defrag) is run. If relative record numbers are sensitive in your application, use the API option to back up database files.

12.6 Limitations

If a library is being journaled, journaling does not start automatically after a restore and a warning appears in the restore log. You must start journaling a library manually after a restore. Journaling does start automatically after a restore for PFs and other objects that are being journaled.

The IBM i Agent does not support the QNTC, QNetWare or QFileSvr.400 file systems. These file systems are automatically excluded from IFS backup jobs. The dev folder is also excluded from IFS backup jobs, to avoid being overwritten during a disaster recovery. To preserve files in the dev folder, copy the files to other folders.

If you have customized *PGM, *SRVPGM or *BNDDIR objects in the QSYS library, they are not backed up in *SYS or *IBM backup jobs. We highly recommend creating a dedicated job to back up and restore customized objects in the QSYS library. Alternatively, create your own SAVSYS tape or DVD image and recover from the SAVSYS image in a disaster recovery.

12.6.1 IFS backup job limitations

IFS device, block, special character and socket files are typically created by the operating system install or operating system running programs. The agent does not restore these objects and some errors will be listed in the log file if you attempt to restore these files.

The following IFS directories are excluded from IFS backups:

/dev

Note: The /dev folder is excluded from IFS backup jobs to avoid being overwritten during a disaster recovery. If you want to preserve files in the /dev folder, copy the files to other folders.


- /QSYS.LIB
- /QOPT
- /QNTC
- /QNetWare
- /QFileSvr.400

The following IFS directory is used for network server storage and can only be backed up when the network servers are varied off: /QFPNWSSTG. We recommend excluding this directory from a root backup.

13 Carbonite Server Backup Support


If you have a question about Carbonite Server Backup that isn't covered in this guide, our frequently-updated Knowledge Base contains comprehensive information. The Knowledge Base is your first stop when searching for any Carbonite Server Backup solutions you may need. We highly recommend searching here first for the quickest answers to your questions.

Knowledge Base: http://support.carbonite.com/evault



13.1 Contacting Carbonite

If you need live assistance from a qualified support agent, Carbonite Support is here for you 24 hours a day, 7 days a week (excluding US holidays). Please feel free to get in touch with us, and we'll help out any way we can! You can find the contact information for Carbonite Support in the Knowledge Base: http://support.carbonite.com/evault



Tip: When contacting Support with a technical issue, please have both the program's log files and the store you are having difficulty with ready.

To gather log files, click **File** menu and choose *Open log folder*. Compress the contents of the folder in a .zip file and attach it to your support request.

If the log archive and/or mail store exceeds 10MB, you may not be able to send them as an email attachment. In that case, upload instructions will be provided to you upon request.